



CAPL Scripting Quickstart

CAPL (Communication Access Programming Language)
For CANalyzer and CANoe

Agenda

► **Before Getting Started**

Visual Sequencer (GUI Based Programming)

Brief Introduction to CAPL


Panel Creation and CAPL

Additional Information

Contact Information


Difference between CANalyzer and CANoe

- ▶ CANoe offers significant additional capability beyond CANalyzer to:
 - > Stimulate the network(s) with **Interaction Layer** knowledge
 - > Run automated tests and generate test reports
 - > Implement automated diagnostic tests



CANoe Interaction Layer

- ▶ The CANoe Interaction Layer (in short CANoeIL):
 - > Provides a signal-oriented means of accessing the bus
 - > Map signals to their appropriate send messages
 - > Controls the sending of these messages as a function of the (OEM) Send Model
- ▶ Transmission of messages and signals is described based on attributes in the database
- ▶ CANoeIL models the transmission behavior at run-time using those attributes



CAPL Support

CAPL is available in CANalyzer PRO and all versions of CANoe

CANalyzer is available in three different variants:

- ▶ PRO: Professional variant: full functionality
- ▶ EXP: Expert variant: supports all applications up to complex analysis of heterogeneous systems; does not support CAPL programs
- ▶ FUN: Fundamental variant: simple applications, does not support CAPL, diagnostic tester and panels

Detailed information about the variants of CANalyzer is available at our website:

http://www.vector.com/vi_canalyzer_variants_en.html

Agenda

Before Getting Started

► **Visual Sequencer (GUI Based Programming)**

Brief Introduction to CAPL

Panel Creation and CAPL

Additional Information

Contact Information

General

- ▶ Available in both CANalyzer PRO and EXP as well as CANoe
 - > Intended to allow some automation within the EXP variant


- ▶ The Visual Sequencer allows you to create *automated command sequences* with the purpose of
 - > Stimulating the network
 - > Controlling applications

- ▶ In order to *structure* the individual steps, loops and conditional command blocks can be used, such as
 - > `if, else if, end if`


- ▶ Each sequence is shown in a *separate window*, and can be edited at any time, even while a measurement is running.

Features

- ▶ Send messages (cyclically)
- ▶ Set signals/variables
- ▶ If, else, else if and repeat commands
- ▶ Wait commands
- ▶ Start/stop replay
- ▶ Write text or values to write window or file
- ▶ Graphical debug
- ▶ Auto complete for names



See Sample Configuration: CAN System Demo (CANsystemdemo.cfg)



The screenshot displays the Visual Sequencer GUI with three main windows:

- DrivingCycle**: A table showing a sequence of commands for a CAN system demo.
- XML Tester**: A window showing a tree view of test cases for the CANSystemDemo XML Test Module.
- Engine Tester**: A window showing a tree view of test cases for the Engine Tester.

DrivingCycle Table:

Command	Object	Operator	Operand	Wait [ms]
Wait	2000	ms		0
Set	PedalPosition	=	0	0
Set	EngineData::EngSpeed	=	0	0
Set	GearBoxInfo::Gear	=	Idle	50
Set	GatewaySwitchIgnition	=	Off	50
Set	GatewaySwitchIgnition	=	Key	50
Set	GatewaySwitchIgnition	=	K15R	50
Set	GatewaySwitchIgnition	=	K15	50
Set	GatewayStarter	=	1	0
Set	GearUp	=	1	0

XML Tester Test Cases:

Test Case Name	Verdict	Runtime
CANSystemDemo XML Test Module		
Start engine	?	
PowerTrain test		
Brake test	?	
Window position on driver's door	?	
Console test		
Lights test		
Turn light left	?	

Engine Tester Test Cases:

Test Case Name	Verdict	Runtime
Engine Tester		

Agenda

Before Getting Started

Visual Sequencer (GUI Based Programming)

► **Brief Introduction to CAPL**

Panel Creation and CAPL

Additional Information

Contact Information

General

Functional blocks based on CAPL (Communication Access Programming Language) can be created to program

- ▶ Network node modules
- ▶ Special evaluation programs for individual applications


Some CAPL characteristics:

- ▶ C-like programming language
- ▶ **Event based**, not interrupt driven
- ▶ CAPL programs are created using an integrated development environment called the CAPL Browser
- ▶ Direct access to signals, system variables and diagnostic parameters
- ▶ Able to link user created DLLs


CANoe

- ▶ Creating and extending simulations
- ▶ Implementing functions for analysis in the measurement setup

Simulation Setup




Measurement Setup




CANalyzer

- ▶ Creating simulations or reactive scripts
- ▶ Implementing functions for analysis in the measurement setup


Send Loop of the Measurement Setup



Analysis Branches




CAPL Browser




Compiling

- In order to generate an executable program file from a CAPL program, the program must be compiled with the CAPL compiler:



- Error messages are shown in the lower Message Window:




When you double-click the error description, the cursor in the *Text Editor* automatically jumps to the point in the source code, where the error originated.

Examining a CAPL Program

```
1  /*@!Encoding:1252*/
2  ▢ includes
3  {
4      // Include files are referenced here
5      #include "D:\Sandbox\Demo\CAPL\TxFilter.can"
6  }
7
8  ▢ variables
9  {
10     // Global Variables are defined here
11     int i;
12     char nameArray[255];
13 }
14
15 ▢ on key 'A'
16 {
17     int j;
18     j = 25;
19
20     write("The value of j is %d", j);
21 }
22
23
24 ▢ void myFunction(int input1, int input2)
25 {
26     // Your function code goes here
27 }
```

- ▶ Additional CAPL files that contain generic code that can be reused in other programs
- ▶ Variables defined here are accessible throughout the CAPL program
- ▶ Multiple pre-defined event handlers exist for your use within CAPL. The code in this handler will only be executed when the event occurs.
- ▶ You can create your own functions (special handler) that contain related code to be executed frequently

Adding Event Handlers



CAPL is a procedural language in which the execution of program blocks is controlled by events. These program blocks are referred to as event procedures.


Important Event Handlers (CAN)

- ▶ Start of measurement



```
on Start
{
    write ("Start of CANoe");
}
```

- ▶ Message received



```
on message 0x123
{
    write ("CAN Message 123");
}
```

- ▶ Signal change



```
on signal sigTemp
{
    write ("Signal Temperature");
}
```

- ▶ Time event



```
on timer tmrCycle
{
    write ("within cycle");
}
```

- ▶ Key press



```
on key 'a'
{
    write ("Key >a< pressed");
}
```

On Key Procedures

```
on key 'a'           // React to press of 'a' key

on key ' '           // React to press of spacebar

on key 0x20           // React to press of spacebar

on key F1            // React to press of F1 key

on key ctrlF12        // React to press of Ctrl-F12

on key PageUp        // React to press of Page Up key

on key Home          // React to press of Home key

on key *             // React to any key press except...
```

Data Types for CAN

Type		Name	Bit	Note
Integers	Signed	<code>int</code>	16	
		<code>long</code>	32	
		<code>int64</code>	64	
	Unsigned	<code>byte</code>	8	
		<code>word</code>	16	
		<code>dword</code>	32	
		<code>qword</code>	64	
Floating point		<code>float</code>	64	Per IEEE
		<code>double</code>	64	Per IEEE
Single character		<code>char</code>	8	
Message variable	for CAN	<code>message</code>		for CAN messages
Time variables	for seconds	<code>timer</code>		for Timer in s
	for milliseconds	<code>mstimer</code>		for Timer in ms


Variables in CAPL

► CAPL code:

```
int i = 100;           // Declaration and initialization of an integer STATIC VARIABLES!!
char ch = 'a';        // Declaration and initialization of a character
float x;              // Declaration of a floating point number

write ("Hundred as decimal number: %d", i);
write ("Hundred as hexadecimal number: %x", i);
write ("Pi as floating point number: %f", pi);
write ("The decimal ASCII code of %c is %d", ch, ch);
write ("The value of x is %f", x);
```

► Results:



String Format Specifiers

Specifier	Description
"%ld", "%d"	decimal display
"%lx", "%x"	hexadecimal display
"%lX", "%X"	hexadecimal display (upper case)
"%lu", "%u"	unsigned display
"%lo", "%o"	octal display
"%s"	display a string
"%g", "%f"	floating point display. e.g. %5.3f means, 5 digits in total (decimal point inclusive) and 3 digits after the decimal point. 5 is the minimum of digits in this case.
"%c"	display a character
"%%"	display %-character
"%I64d", "%lld"	decimal display of a 64 bit value
"%I64x", "%llx"	hexadecimal display of a 64 bit value
"%I64X", "%llX"	hexadecimal display of a 64 bit value (upper case)
"%I64u", "%llu"	unsigned display of a 64 bit value
"%I64o", "%llo"	octal display of a 64 bit value

Operators

Operator	Description	Example
+ -	Addition, subtraction	-
* /	Multiplication, division	-
++ --	Increment or decrement by 1	<code>a++; // increments a by 1</code>
%	Modulo division (returns integer remainder of a division)	<code>a = 4 % 3; // a is 1</code>
< <=	Less than; less than or equal to	returns TRUE or FALSE
> >=	Greater than; greater than or equal to	returns TRUE or FALSE
== !=	Compare for equality or inequality	returns TRUE or FALSE
&&	Logic AND	returns TRUE or FALSE
	Logic OR	returns TRUE or FALSE
!	Logic NOT	changes TRUE to FALSE and vice versa
&	Bitwise AND	<code>1 & 7 // yields 1 (0001 & 0111 → 0001)</code>
	Bitwise OR	<code>1 7 // yields 7 (0001 0111 → 0111)</code>
~	Bitwise complement	<code>~1 // yields 14 (0001 → 1110)</code>
^	Bitwise exclusive OR (XOR)	<code>01^11 // ergibt 10</code>
>> <<	Bit shift to right or left	<code>1 << 3 // yields 8 (0001 → 1000)</code>

Agenda

Before Getting Started

Visual Sequencer (GUI Based Programming)

Brief Introduction to CAPL


► **Panel Creation and CAPL**

Additional Information

Contact Information


Creating a Panel

- ▶ A signal can be mapped to each display or control as simple as drag and drop
- ▶ CANalyzer display only controls for signals



Creating System Variables

- ▶ System Variables can be system defined or user defined.
- ▶ The variables can be created, saved, imported and exported.



Agenda

Before Getting Started

Visual Sequencer (GUI Based Programming)

Brief Introduction to CAPL

Panel Creation and CAPL

► **Additional Information**

Contact Information

Online Help File

Vector | CANoe & Modules

Contents | Index | Search | Favorites

- CANoe
- Sample Configurations
- CANdb++
- CAPL Browser
- CAPL Introduction
 - Start Page
 - Glossary
 - CAPL Warnings
- Basics
 - Structure of a CAPL Program
 - Compile a CAPL Program
 - Working with Databases
 - Access to Values/Signals in CAPL
 - Tips
- CAPL Functions
- Debugger
- Panel Designer
- FDX Editor
- Option CANoe .DiVa
- Vector Pool License Dialog
- Technical References

CAPL Introduction

CANoe > CAPL > Introduction

Topic search

Screenshot

```

on start
{
    // net-management
    // set to 2 to get more information
    setWriteDbgLevel(1);
    writeDbgLevel(2,gECU);

```

Quick Access

Glossary

CAPL Browser

Online help for all CAPL functions:

Technical Reference: CAPL Functions

CAPL Basics

- CAPL
- Introduction to CAPL

Structure of a CAPL Program

- Variables
- Include Files
- Event Procedures
- Functions

Procedures

- Compile a CAPL Program
- Working with Databases

Direct Access to Values/Signals in CAPL

Diagnostics

- Usage of Diagnostic Objects in CAPL
- Filter Diagnostic Objects using CAPL Filter in the Measurement Setup

Direct Access to Variable Values

- Direct Access to Values from System Variables
- Direct Access to Values from Environment Variables

Test

- Test Service Library: CAPL Test Modules
- Test Service Library: CAPL Simulation Nodes
- Constraints and Conditions (CAPL)

Direct Access to Signals

- Concept of a Signal in CAPL
- Signal Qualification for Signal Ambiguity
- Reading Signal Values (Raw or Physical Value)
- Setting Signal Values
- Response to Signal Changes
- Signals as Function Parameters
- Heuristics for Signal Identification

FlexRay

Agenda

Before Getting Started

Visual Sequencer (GUI Based Programming)

Brief Introduction to CAPL

Panel Creation and CAPL

Additional Information

► **Contact Information**

Looking for more information?

Visit our website:

> <http://www.vector.com>

Sign in for a Vector training class:

> http://www.vector.com/vi_training_en.html

Need help with Vector tools?

Contact our support team:

> (248) 449 – 9290 Option 2

> support@us.vector.com

My contact info:

> Shawn.Kaschner@vector.com

Your questions are welcome!

Author:
Kaschner, Shawn
Vector North America